



Windows PowerShell Get-Help on Cmdlet 'Get-AzDataFactoryDataset'

PS:\>Get-HELP Get-AzDataFactoryDataset -Full

NAME

Get-AzDataFactoryDataset

SYNTAX

```
Get-AzDataFactoryDataset [-ResourceGroupName] <string> [-DataFactoryName] <string> [[-Name] <string>]
[-DefaultProfile <IAzureContextContainer>] [<CommonParameters>]
```

```
Get-AzDataFactoryDataset [-DataFactory] <PSDataFactory> [[-Name] <string>] [-DefaultProfile
<IAzureContextContainer>] [<CommonParameters>]
```

PARAMETERS

-DataFactory <PSDataFactory>

The data factory object.

Required? true

Position? 0

Accept pipeline input? true (ByPropertyName)

Parameter set name ByFactoryObject

Aliases None

Dynamic? false

-DataFactoryName <string>

The data factory name.

Required? true

Position? 1

Accept pipeline input? true (ByPropertyName)

Parameter set name ByFactoryName

Aliases None

Dynamic? false

-DefaultProfile <IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? Named

Accept pipeline input? false

Parameter set name (All)

Aliases AzContext, AzureRmContext, AzureCredential

Dynamic? false

-Name <string>

The dataset name.

Required? false

Position? 2

Accept pipeline input? true (ByPropertyName)

Parameter set name (All)

Aliases None

Dynamic? false

-ResourceGroupName <string>

The resource group name.

Required?	true
Position?	0
Accept pipeline input?	true (ByPropertyName)
Parameter set name	ByFactoryName
Aliases	None
Dynamic?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.DataFactories.Models.PSDataFactory
System.String

OUTPUTS

Microsoft.Azure.Commands.DataFactories.Models.PSDataset

ALIASES

None

REMARKS

None

