



Windows PowerShell Get-Help on Cmdlet 'Get-AzDataFactoryHub'

PS:\>Get-HELP Get-AzDataFactoryHub -Full

NAME

Get-AzDataFactoryHub

SYNTAX

Get-AzDataFactoryHub [-ResourceGroupName] <string> [-DataFactoryName] <string> [[-Name] <string>] [-DefaultProfile <IAzureContextContainer>] [<CommonParameters>]

Get-AzDataFactoryHub [-DataFactory] <PSDataFactory> [[-Name] <string>] [-DefaultProfile <IAzureContextContainer>] [<CommonParameters>]

PARAMETERS

-DataFactory <PSDataFactory>

The data factory object.

Required? true

Position? 0

Accept pipeline input? true (ByPropertyName)

Parameter set name ByFactoryObject

Aliases None

Dynamic? false

-DataFactoryName <string>

The data factory name.

Required? true

Position? 1

Accept pipeline input? true (ByPropertyName)

Parameter set name ByFactoryName

Aliases None

Dynamic? false

-DefaultProfile <IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? Named

Accept pipeline input? false

Parameter set name (All)

Aliases AzContext, AzureRmContext, AzureCredential

Dynamic? false

-Name <string>

The hub name.

Required? false

Position? 2

Accept pipeline input? true (ByPropertyName)

Parameter set name (All)

Aliases None

Dynamic? false

-ResourceGroupName <string>

The resource group name.

Required?	true
Position?	0
Accept pipeline input?	true (ByPropertyName)
Parameter set name	ByFactoryName
Aliases	None
Dynamic?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String
Microsoft.Azure.Commands.DataFactories.Models.PSDataFactory

OUTPUTS

Microsoft.Azure.Commands.DataFactories.Models.PSHub

ALIASES

None

REMARKS

None

