



Windows PowerShell Get-Help on Cmdlet 'Get-AzDataFactoryLinkedService'

PS: \>Get-HELP Get-AzDataFactoryLinkedService -Full

NAME

Get-AzDataFactoryLinkedService

SYNTAX

```
Get-AzDataFactoryLinkedService [-ResourceGroupName] <string> [-DataFactoryName] <string> [[-Name] <string>]
[-DefaultProfile <IAzureContextContainer>]
[<CommonParameters>]
```

```
Get-AzDataFactoryLinkedService [-DataFactory] <PSDataFactory> [[-Name] <string>] [-DefaultProfile
<IAzureContextContainer>] [<CommonParameters>]
```

PARAMETERS

-DataFactory <PSDataFactory>

The data factory object.

Required? true

Position? 0

Accept pipeline input? true (ByPropertyName)

Parameter set name ByFactoryObject

Aliases	None
Dynamic?	false

-DataFactoryName <string>

The data factory name.

Required?	true
Position?	1
Accept pipeline input?	true (ByPropertyName)
Parameter set name	ByFactoryName
Aliases	None
Dynamic?	false

-DefaultProfile <IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	AzContext, AzureRmContext, AzureCredential
Dynamic?	false

-Name <string>

The linked service name.

Required?	false
Position?	2
Accept pipeline input?	true (ByPropertyName)
Parameter set name	(All)
Aliases	None
Dynamic?	false

-ResourceGroupName <string>

The resource group name.

Required? true

Position? 0

Accept pipeline input? true (ByPropertyName)

Parameter set name ByFactoryName

Aliases None

Dynamic? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.DataFactories.Models.PSDataFactory

System.String

OUTPUTS

Microsoft.Azure.Commands.DataFactories.Models.PSLinkedService

ALIASES

None

REMARKS

None

