



Windows PowerShell Get-Help on Cmdlet 'Get-AzDataFactoryV2TriggerSubscriptionStatus'

PS:\>Get-HELP Get-AzDataFactoryV2TriggerSubscriptionStatus -Full

NAME

Get-AzDataFactoryV2TriggerSubscriptionStatus

SYNOPSIS

Get the status of the subscription for the event trigger to the specified external service events.

SYNTAX

```
Get-AzDataFactoryV2TriggerSubscriptionStatus [-ResourceGroupName] <String> [-DataFactoryName] <String> [-Name]
<String> [-DefaultProfile <IAzureContextContainer>]
[<CommonParameters>]
```

```
Get-AzDataFactoryV2TriggerSubscriptionStatus [-InputObject] <PSTrigger> [-DefaultProfile <IAzureContextContainer>]
[<CommonParameters>]
```

```
Get-AzDataFactoryV2TriggerSubscriptionStatus [-ResourceId] <String> [-DefaultProfile <IAzureContextContainer>]
[<CommonParameters>]
```

DESCRIPTION

This command gets the status of the subscription for the event trigger to the specified external service events. The trigger can't be started until the returned status is "Enabled".

PARAMETERS

-DataFactoryName <String>

The data factory name.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <PSTrigger>

The trigger object.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <String>

The trigger name.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <String>

The resource group name.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceId <String>

The Azure resource ID.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.DataFactoryV2.Models.PSTrigger

OUTPUTS

Microsoft.Azure.Commands.DataFactoryV2.Models.PSTriggerSubscriptionStatus

NOTES

----- Example 1 -----

```
Get-AzDataFactoryV2TriggerSubscriptionStatus -ResourceGroupName ADF -DataFactoryName WikiADF -Name  
Trigger1
```

TriggerName	Status
-------------	--------

-----	-----
-------	-------

Trigger1	Enabled
----------	---------

This command will get the status of the subscription for BlobEnetTrigger1 trigger to the external service events.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.datafactory/get-azdatafactoryv2triggersubscriptionstatus>

