



Windows PowerShell Get-Help on Cmdlet 'Get-AzDatabricksOutboundNetworkDependenciesEndpoint'

PS:\>Get-HELP Get-AzDatabricksOutboundNetworkDependenciesEndpoint -Full

NAME

Get-AzDatabricksOutboundNetworkDependenciesEndpoint

SYNOPSIS

Gets the list of endpoints that VNET Injected Workspace calls Azure Databricks Control Plane.

You must configure outbound access with these endpoints.

For more information, see

<https://docs.microsoft.com/en-us/azure/databricks/administration-guide/cloud-configurations/azure/udr>

SYNTAX

```
Get-AzDatabricksOutboundNetworkDependenciesEndpoint -ResourceGroupName <String> -WorkspaceName <String>
[-SubscriptionId <String[]>] [-DefaultProfile <PSObject>]
[-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Gets the list of endpoints that VNET Injected Workspace calls Azure Databricks Control Plane.

You must configure outbound access with these endpoints.

For more information, see

<https://docs.microsoft.com/en-us/azure/databricks/administration-guide/cloud-configurations/azure/udr>

PARAMETERS

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-WorkspaceName <String>

The name of the workspace.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Databricks.Models.Api20230201.IOutboundEnvironmentEndpoint

----- EXAMPLE 1 -----

```
PS C:\>Get-AzDatabricksOutboundNetworkDependenciesEndpoint -ResourceGroupName azps_test_gp_db  
-WorkspaceName azps-databricks-workspace-t2
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.databricks/get-azdatabricksoutboundnetworkdependenciesendpoint>