



Windows PowerShell Get-Help on Cmdlet 'Get-AzDefault'

PS:\>Get-HELP Get-AzDefault -Full

NAME

Get-AzDefault

SYNOPSIS

Get the defaults set by the user in the current context.

SYNTAX

	Get-AzDefault	[-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>		[-ResourceGroup]
[<CommonParameters>]		

DESCRIPTION

The Get-AzDefault cmdlet gets the Resource Group that the user has set as default in the current context.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-ResourceGroup <System.Management.Automation.SwitchParameter>

Display Default Resource Group

Required?	false
Position?	named
Default value	False
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.Management.Automation.SwitchParameter

OUTPUTS

Microsoft.Azure.Commands.Profile.Models.PSResourceGroup

----- Example 1 -----

Get-AzDefault

Id : /subscriptions/xxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxx/resourceGroups/myResourceGroup
Name : myResourceGroup
Properties : Microsoft.Azure.Management.Internal.Resources.Models.ResourceGroupProperties
Location : eastus
ManagedBy :
Tags :

This command returns the current defaults if there are defaults set, or returns nothing if no default is set.

----- Example 2 -----

Get-AzDefault -ResourceGroup

Id : /subscriptions/xxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxx/resourceGroups/myResourceGroup
Name : myResourceGroup
Properties : Microsoft.Azure.Management.Internal.Resources.Models.ResourceGroupProperties
Location : eastus
ManagedBy :
Tags :

This command returns the current default Resource Group if there is a default set, or returns nothing if no default is set.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.accounts/get-azdefault>