



Windows PowerShell Get-Help on Cmdlet 'Get-AzEventHubClustersAvailableRegion'

PS:\>Get-HELP Get-AzEventHubClustersAvailableRegion -Full

NAME

Get-AzEventHubClustersAvailableRegion

SYNOPSIS

List the quantity of available pre-provisioned Event Hubs Clusters, indexed by Azure region.

SYNTAX

```
Get-AzEventHubClustersAvailableRegion [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
    <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]
```

DESCRIPTION

List the quantity of available pre-provisioned Event Hubs Clusters, indexed by Azure region.

PARAMETERS

-SubscriptionId <String[]>

Subscription credentials that uniquely identify a Microsoft Azure subscription.

The subscription ID forms part of the URI for every service call.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.EventHub.Models.IAvailableClustersList

----- EXAMPLE 1 -----

```
PS C:\>Get-AzEventHubClustersAvailableRegion
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.eventhub/get-azeventhubclustersavailableregion>

