



## ***Windows PowerShell Get-Help on Cmdlet 'Get-AzEventHubPrivateLink'***

***PS:\>Get-HELP Get-AzEventHubPrivateLink -Full***

### NAME

Get-AzEventHubPrivateLink

### SYNOPSIS

Gets lists of resources that supports Privatelinks.

### SYNTAX

```
Get-AzEventHubPrivateLink -NamespaceName <String> -ResourceGroupName <String> [-SubscriptionId <String[]>]
[-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend
    <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

### DESCRIPTION

Gets lists of resources that supports Privatelinks.

### PARAMETERS

-NamespaceName <String>

The Namespace name

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

Name of the resource group within the azure subscription.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

Subscription credentials that uniquely identify a Microsoft Azure subscription.

The subscription ID forms part of the URI for every service call.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

#### **-ProxyCredential <PSCredential>**

Credentials for a proxy server to use for the remote call

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

#### **-ProxyUseDefaultCredentials [<SwitchParameter>]**

Use the default credentials for the proxy

Required? false  
Position? named  
Default value False  
Accept pipeline input? false  
Accept wildcard characters? false

#### **<CommonParameters>**

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

## **INPUTS**

## OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.EventHub.Models.IPrivateLinkResourcesListResult

----- EXAMPLE 1 -----

```
PS C:\>Get-AzEventHubPrivateLink -ResourceGroupName myResourceGroup -NamespaceName myNamespace
```

## RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.eventhub/get-azeventhubprivatelink>

<https://msdn.microsoft.com/en-us/library/azure/mt639379.aspx>