



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Get-AzExpressRoutePortLinkConfig'

PS:\>Get-HELP Get-AzExpressRoutePortLinkConfig -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Get-AzExpressRoutePortLinkConfig

SYNOPSIS

Gets an ExpressRoutePort link configuration.

SYNTAX

Get-AzExpressRoutePortLinkConfig [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -ExpressRoutePort

<Microsoft.Azure.Commands.Network.Models.PSExpressRoutePort> [-Name <System.String>] [<CommonParameters>]

Get-AzExpressRoutePortLinkConfig [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -ExpressRoutePort

<Microsoft.Azure.Commands.Network.Models.PSExpressRoutePort> -ResourceId <System.String>

[<CommonParameters>]

DESCRIPTION

The Get-AzExpressRoutePortLinkConfig cmdlet retrieves the configuration of a link of an ExpressRoutePort.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ExpressRoutePort <Microsoft.Azure.Commands.Network.Models.PSExpressRoutePort>

The reference of the ExpressRoutePort resource.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-Name <System.String>

Name of the link.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

ResourceId of the link.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Network.Models.PSExpressRoutePort

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSExpressRouteLink

NOTES

----- Example 1 -----

```
Get-AzExpressRoutePortLinkConfig -ExpressRoutePort $erport -Name Link1
```

Gets the Link1 configuration of ExpressRoutePort \$erport

----- Example 2 -----

```
Get-AzExpressRoutePortLinkConfig -ExpressRoutePort $erport -ResourceId $id
```

Gets the configuration of link with Resourceld \$id in ExpressRoutePort \$erport

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/get-azexpressrouteportlinkconfig>