



Windows PowerShell Get-Help on Cmdlet 'Get-AzFrontDoorCdnOriginGroupResourceUsage'

PS:\>Get-HELP Get-AzFrontDoorCdnOriginGroupResourceUsage -Full

NAME

Get-AzFrontDoorCdnOriginGroupResourceUsage

SYNOPSIS

Checks the quota and actual usage of endpoints under the given Azure Front Door profile..

SYNTAX

```
Get-AzFrontDoorCdnOriginGroupResourceUsage -OriginGroupName <String> -ProfileName <String>
-ResourceGroupName <String> [-SubscriptionId <String>] [-DefaultProfile
    <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy
    <Uri>] [-ProxyCredential <PSCredential>]
    [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Checks the quota and actual usage of endpoints under the given Azure Front Door profile..

-OriginGroupName <String>

Name of the origin group which is unique within the endpoint.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProfileName <String>

Name of the Azure Front Door Standard or Azure Front Door Premium profile which is unique within the resource group.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

Name of the Resource group within the Azure subscription.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

Azure Subscription ID.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Cdn.Models.Api20240201.IUsage

----- EXAMPLE 1 -----

fdp-v542q6 -OriginGroupName org001

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.cdn/get-azfrontdoorcdnorigingroupresourceusage>