



Windows PowerShell Get-Help on Cmdlet 'Get-AzKeyVaultCertificateIssuer'

PS:\>Get-HELP Get-AzKeyVaultCertificateIssuer -Full

NAME

Get-AzKeyVaultCertificateIssuer

SYNOPSIS

Gets a certificate issuer for a key vault.

SYNTAX

```
Get-AzKeyVaultCertificateIssuer [-InputObject] <Microsoft.Azure.Commands.KeyVault.Models.PSKeyVault> [[-Name]
<System.String>] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

```
Get-AzKeyVaultCertificateIssuer [-ResourceId] <System.String> [[-Name] <System.String>] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

```
Get-AzKeyVaultCertificateIssuer [-VaultName] <System.String> [[-Name] <System.String>] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

DESCRIPTION

The Get-AzKeyVaultCertificateIssuer cmdlet gets a specified certificate issuer or all certificate issuers for a key vault in Azure Key Vault.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.KeyVault.Models.PSKeyVault>

KeyVault object.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the certificate issuer to get.

Required? false

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? true

-ResourceId <System.String>

KeyVault Resource Id.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-VaultName <System.String>

Specifies the name of a key vault.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.KeyVault.Models.PSKeyVault

System.String

OUTPUTS

Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateIssuerIdentityItem

Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateIssuer

NOTES

----- Example 1: Get a certificate issuer -----

Get-AzKeyVaultCertificateIssuer -VaultName "Contosokv01" -Name "TestIssuer01"

AccountId : 555

ApiKey :

OrganizationDetails : Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateOrganizationDetails

Name : TestIssuer01

IssuerProvider : Test

VaultName : Contosokv01

This command gets the certificate issuer named TestIssuer01.

----- Example 2: List certificate issuers using filtering -----

Get-AzKeyVaultCertificateIssuer -VaultName "Contosokv01" -Name "test*"

AccountId : 555

ApiKey :

OrganizationDetails : Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateOrganizationDetails

Name : TestIssuer01

IssuerProvider : Test

VaultName : Contosokv01

AccountId : 555

ApiKey :

OrganizationDetails : Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateOrganizationDetails

Name : TestIssuer02

IssuerProvider : Test

VaultName : Contosokv01

This command gets the certificate issuers that start with "test".

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.keyvault/get-azkeyvaultcertificateissuer>

Remove-AzKeyVaultCertificateIssuer

Set-AzKeyVaultCertificateIssuer