



Windows PowerShell Get-Help on Cmdlet 'Get-AzKustoDatabasePrincipal'

PS:\>Get-HELP Get-AzKustoDatabasePrincipal -Full

NAME

Get-AzKustoDatabasePrincipal

SYNOPSIS

Returns a list of database principals of the given Kusto cluster and database.

SYNTAX

```
Get-AzKustoDatabasePrincipal -ClusterName <String> -DatabaseName <String> -ResourceGroupName <String>
[-SubscriptionId <String[]>] [-DefaultProfile <PSObject>]
[-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Returns a list of database principals of the given Kusto cluster and database.

-ClusterName <String>

The name of the Kusto cluster.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DatabaseName <String>

The name of the database in the Kusto cluster.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Kusto.Models.Api20230815.IDatabasePrincipal

----- EXAMPLE 1 -----

mykustodatabase

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.kusto/get-azkustodatabaseprincipal>