



## ***Windows PowerShell Get-Help on Cmdlet 'Get-AzLoadBalancerOutboundRuleConfig'***

***PS:\>Get-HELP Get-AzLoadBalancerOutboundRuleConfig -Full***

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

### **NAME**

Get-AzLoadBalancerOutboundRuleConfig

### **SYNOPSIS**

Gets an outbound rule configuration in a load balancer.

### **SYNTAX**

```
Get-AzLoadBalancerOutboundRuleConfig [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -LoadBalancer  
<Microsoft.Azure.Commands.Network.Models.PSLoadBalancer> [-Name <System.String>] [<CommonParameters>]
```

### **DESCRIPTION**

The Get-AzLoadBalancerOutboundRuleConfig cmdlet gets an outbound rule configuration or a list of outbound rule configurations in a load balancer.

## PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-LoadBalancer <Microsoft.Azure.Commands.Network.Models.PSLoadBalancer>

The reference of the load balancer resource.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-Name <System.String>

Name of the outbound rule.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (https://go.microsoft.com/fwlink/?LinkID=113216).

## INPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

## OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSOutboundRule

## NOTES

Example 1: Get an outbound rule configuration in a load balancer

```
$slb = Get-AzLoadBalancer -ResourceGroupName "MyResourceGroup" -Name "MyLoadBalancer"  
Get-AzLoadBalancerOutboundRuleConfig -LoadBalancer $slb -Name "MyRule"
```

The first command gets the load balancer named MyLoadBalancer, and then stores it in the variable \$slb. The second command gets the outbound rule configuration named

MyRule associated with that load balancer.

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/get-azloadbalanceroutboundruleconfig>

Add-AzLoadBalancerOutboundRuleConfig

New-AzLoadBalancerOutboundRuleConfig

Remove-AzLoadBalancerOutboundRuleConfig

Set-AzLoadBalancerOutboundRuleConfig