



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Get-AzMaintenanceConfiguration'***

**PS:\>Get-HELP Get-AzMaintenanceConfiguration -Full**

#### **NAME**

Get-AzMaintenanceConfiguration

#### **SYNOPSIS**

Get Maintenance configuration record

#### **SYNTAX**

```
Get-AzMaintenanceConfiguration [[-ResourceGroupName] <System.String>] [[-Name] <System.String>] [-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [<CommonParameters>]
```

#### **DESCRIPTION**

Get Maintenance configuration record

#### **PARAMETERS**

**-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>**

The credentials, account, tenant, and subscription used for communication with Azure.

**Page 1/4**

Required? false  
Position? named  
Default value None  
Accept pipeline input? False  
Accept wildcard characters? false

#### -Name <System.String>

The maintenance configuration Name.

Required? false  
Position? 1  
Default value None  
Accept pipeline input? True (ByPropertyName)  
Accept wildcard characters? false

#### -ResourceGroupName <System.String>

The resource Group Name.

Required? false  
Position? 0  
Default value None  
Accept pipeline input? True (ByPropertyName)  
Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

## INPUTS

System.String

## OUTPUTS

Microsoft.Azure.Commands.Maintenance.Models.PSMaintenanceConfiguration

## NOTES

----- Example 1 -----

```
Get-AzMaintenanceConfiguration -ResourceGroupName smdtest -Name workervmscentralus
```

Location : centralus

Tags : {}

NamespaceProperty :

ExtensionProperties : {}

MaintenanceScope : Host

Id :

/subscriptions/42c974dd-2c03-4f1b-96ad-b07f050aaa74/resourcegroups/smdtest/providers/Microsoft.Maintenance/maintenanceConfigurations/workervmscentralus

Name : workervmscentralus

Type : Microsoft.Maintenance/maintenanceConfigurations

Get Maintenance configuration record

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.maintenance/get-azmaintenanceconfiguration>