



Windows PowerShell Get-Help on Cmdlet 'Get-AzMigrateProject'

PS:\>Get-HELP Get-AzMigrateProject -Full

NAME

Get-AzMigrateProject

SYNOPSIS

Method to get a migrate project.

SYNTAX

```
Get-AzMigrateProject -Name <String> -ResourceGroupName <String> [-SubscriptionId <String[]>] [-DefaultProfile  
<PSObject>] [-Break] [-HttpPipelineAppend  
<SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]  
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Method to get a migrate project.

PARAMETERS

-Name <String>

Name of the Azure Migrate project.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

Name of the Azure Resource Group that migrate project is part of.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

Azure Subscription Id in which migrate project was created.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

----- EXAMPLE 1 -----

```
PS C:\>Get-AzMigrateProject -SubscriptionId xxx-xxx-xxx -ResourceGroupName BugBashAVSVMware -Name  
BugBashAVSVMware
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.migrate/get-azmigrateproject>