



Windows PowerShell Get-Help on Cmdlet 'Get-AzMigrateReplicationProtectionContainerMapping'

PS:\>Get-HELP Get-AzMigrateReplicationProtectionContainerMapping -Full

NAME

Get-AzMigrateReplicationProtectionContainerMapping

SYNOPSIS

Gets the details of a protection container mapping.

SYNTAX

```
Get-AzMigrateReplicationProtectionContainerMapping -ResourceGroupName <String> -ResourceName <String>  
[-SubscriptionId <String[]>] [-DefaultProfile <PSObject>]  
[-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]  
[-ProxyCredential <PSCredential>]  
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzMigrateReplicationProtectionContainerMapping -ResourceGroupName <String> -ResourceName <String>  
-FabricName <String> -ProtectionContainerName <String>  
[-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]  
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]  
[-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```

Get-AzMigrateReplicationProtectionContainerMapping -ResourceGroupName <String> -ResourceName <String>
-FabricName <String> -MappingName <String>

-ProtectionContainerName <String> [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]

```

DESCRIPTION

Gets the details of a protection container mapping.

PARAMETERS

-ResourceGroupName <String>

The name of the resource group where the recovery services vault is present.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceName <String>

The name of the recovery services vault.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-FabricName <String>

Fabric name.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-MappingName <String>

Protection Container mapping name.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProtectionContainerName <String>

Protection container name.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-SubscriptionId <String[]>

Azure Subscription Id in which migrate project was created.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Migrate.Models.Api202301.IProtectionContainerMapping

----- EXAMPLE 1 -----

```
PS C:\>Get-AzMigrateReplicationProtectionContainerMapping -ResourceGroupName azmigratepwshtestasr13072020
-ResourceName AzMigrateTestProjectPWSH02aarsvault
               -FabricName      AzMigratePWSHTc8d1replicationfabric      -ProtectionContainerName
AzMigratePWSHTc8d1replicationcontainer -MappingName "containermapping"
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.migrate/get-azmigratereplicationprotectioncontainermapping>