



Windows PowerShell Get-Help on Cmdlet 'Get-AzMigrateRunAsAccount'

PS: \>Get-HELP Get-AzMigrateRunAsAccount -Full

NAME

Get-AzMigrateRunAsAccount

SYNOPSIS

Method to get run as account.

SYNTAX

```
Get-AzMigrateRunAsAccount -ResourceGroupName <String> -SiteName <String> [-SubscriptionId <String[]>]
[-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend
<SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzMigrateRunAsAccount -ResourceGroupName <String> -SiteName <String> -AccountName <String>
[-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
<PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]
```

DESCRIPTION

Method to get run as account.

PARAMETERS

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SiteName <String>

Site name.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AccountName <String>

Run as account ARM name.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Migrate.Models.Api202001.IVMwareRunAsAccount

----- EXAMPLE 1 -----

```
PS C:\>Get-AzMigrateRunAsAccount -SubscriptionId xxx-xxx-xxx -ResourceGroupName BugBashAVSVMware  
-SiteName BBVMwareAVScbbcsite
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzMigrateRunAsAccount -SubscriptionId xxx-xxx-xxx -ResourceGroupName BugBashAVSVMware  
-SiteName BBVMwareAVScbbcsite -AccountName
```

b090bef3-b733-5e34-bc8f-eb6f2701432a

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.migrate/get-azmigraterunasaccount>