



Windows PowerShell Get-Help on Cmdlet 'Get-AzNetworkManagerStaticMember'

PS:\>Get-HELP Get-AzNetworkManagerStaticMember -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Get-AzNetworkManagerStaticMember

SYNOPSIS

Gets network manager static members.

SYNTAX

```

Get-AzNetworkManagerStaticMember [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
<System.String>]
    -NetworkGroupName <System.String> -NetworkManagerName <System.String> -ResourceGroupName <System.String>
[<CommonParameters>]
  
```

```

Get-AzNetworkManagerStaticMember [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name <System.String>
  
```

-NetworkGroupName <System.String> -NetworkManagerName <System.String> -ResourceGroupName <System.String>
[<CommonParameters>]

DESCRIPTION

The Get-AzNetworkManagerStaticMember cmdlet gets a network manager static member.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Name <System.String>

The resource name.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	true

-NetworkGroupName <System.String>

The network manager group name.

Required?	true
Position?	named

Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? true

-NetworkManagerName <System.String>

The network manager name.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? true

-ResourceGroupName <System.String>

The resource group name.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? true

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Network.Models.NetworkManager.PSNetworkManagerStaticMember

NOTES

----- Example 1 -----

```
Get-AzNetworkManagerStaticMember -Name "TestStaticMember" -NetworkManagerName "TestNMName"
-ResourceGroupName "TestRG" -NetworkGroupName "TestNetworkGroup"
```

```
Name          : TestSM
Id             :
/subscriptions/00000000-0000-0000-0000-000000000000/resourceGroups/testRG/providers/Microsoft.Network/networkMan
agers/TestNMName/networkGroups/Test
NetworkGroup/staticMembers/TestStaticMember
ResourceId     :
/subscriptions/00000000-0000-0000-0000-000000000000/resourceGroups/testRG/providers/Microsoft.Network/virtualNetwo
rks/vnet1
Description    :
Type           : Microsoft.Network/networkManagers/networkGroups/staticMembers
Etag           :
ProvisioningState : Succeeded
```

Gets a single static member.

----- Example 2 -----

```
Get-AzNetworkManagerStaticMember -NetworkManagerName "psNetworkManager" -ResourceGroupName  
"psResourceGroup" -NetworkGroupName "psNetworkGroup"
```

```
Name      : TestSM  
Id        :  
/subscriptions/00000000-0000-0000-0000-000000000000/resourceGroups/testRG/providers/Microsoft.Network/networkMan  
agers/TestNMName/networkGroups/Test  
NetworkGroup/staticMembers/TestSM  
ResourceId :  
/subscriptions/00000000-0000-0000-0000-000000000000/resourceGroups/testRG/providers/Microsoft.Network/virtualNetwo  
rks/vnet1  
Description :  
Type        : Microsoft.Network/networkManagers/networkGroups/staticMembers  
Etag        :  
ProvisioningState : Succeeded
```

```
Name      : TestSM2  
Id        :  
/subscriptions/00000000-0000-0000-0000-000000000000/resourceGroups/testRG/providers/Microsoft.Network/networkMan  
agers/TestNMName/networkGroups/Test  
NetworkGroup/staticMembers/TestSM2  
ResourceId :  
/subscriptions/00000000-0000-0000-0000-000000000000/resourceGroups/testRG/providers/Microsoft.Network/virtualNetwo  
rks/vnet2  
Description :  
Type        : Microsoft.Network/networkManagers/networkGroups/staticMembers  
Etag        :  
ProvisioningState : Succeeded
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/get-aznetworkmanagerstaticmember>

New-AzNetworkManagerStaticMember

Remove-AzNetworkManagerStaticMember