



Windows PowerShell Get-Help on Cmdlet 'Get-AzPostgreSqlFlexibleServerLocationBasedCapability'

PS:\>Get-HELP Get-AzPostgreSqlFlexibleServerLocationBasedCapability -Full

NAME

Get-AzPostgreSqlFlexibleServerLocationBasedCapability

SYNOPSIS

Get the available SKU information for the location

SYNTAX

```
Get-AzPostgreSqlFlexibleServerLocationBasedCapability -Location <String> [-SubscriptionId <String[]>] [-DefaultProfile  
<PSObject>] [-Break] [-HttpPipelineAppend  
<SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]  
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Get the available SKU information for the location

PARAMETERS

-Location <String>

The name of the location.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,
ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.PostgreSql.Models.Api20210601.ICapabilityProperties

----- EXAMPLE 1 -----

PS C:\>Get-AzPostgreSqlFlexibleServerLocationBasedCapability -Location eastus

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.postgresql/get-azpostgresqlflexibleserverlocationbasedcapability>