



Windows PowerShell Get-Help on Cmdlet 'Get-AzRedisEnterpriseCacheOperationStatus'

PS:\>Get-HELP Get-AzRedisEnterpriseCacheOperationStatus -Full

NAME

Get-AzRedisEnterpriseCacheOperationStatus

SYNOPSIS

Gets the status of operation.

SYNTAX

Get-AzRedisEnterpriseCacheOperationStatus -Location <String> -OperationId <String> [-SubscriptionId <String[]>]
[-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
<PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]

DESCRIPTION

Gets the status of operation.

PARAMETERS

-Location <String>

The name of Azure region.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-OperationId <String>

The ID of an ongoing async operation.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.RedisEnterpriseCache.Models.Api20230301Preview.IOperationStatus

----- EXAMPLE 1 -----

```
PS C:\>Get-AzRedisEnterpriseCacheOperationStatus -Location "East US" -OperationId  
"6432a8f9-0fe6-4339-9303-772c92f35d02"
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.redisenterprise/cache/get-azredisenterpriseoperationstatus>