



Windows PowerShell Get-Help on Cmdlet 'Get-AzResourceGroupDeploymentStack'

PS:\>Get-HELP Get-AzResourceGroupDeploymentStack -Full

NAME

Get-AzResourceGroupDeploymentStack

SYNOPSIS

Gets Resource Group scoped Deployment Stacks.

SYNTAX

```
Get-AzResourceGroupDeploymentStack [-ResourceGroupName] <System.String> [-Name] <System.String>
[-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Pre]
[<CommonParameters>]
```

```
Get-AzResourceGroupDeploymentStack [-ResourceGroupName] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Pre]
[<CommonParameters>]
```

```
Get-AzResourceGroupDeploymentStack [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Pre] -ResourceId
    <System.String> [<CommonParameters>]
```

DESCRIPTION

Retrieve a resource group scoped deployment stack.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The name of the DeploymentStack to get

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Pre <System.Management.Automation.SwitchParameter>

When set, indicates that the cmdlet should use pre-release API versions when automatically determining which version to use.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

The id of the ResourceGroup where the DeploymentStack is deployed

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceId <System.String>

ResourceId of the DeploymentStack to get

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

NOTES

Example 1: Retrieve a stack named MyRGStack from the resource group MyResourceGroup

```
Get-AzResourceGroupDeploymentStack -ResourceGroupName MyResourceGroup -Name MyRGStack
```

Get a deployment stack named 'MyRGStack' under an RG named 'MyResourceGroup'.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.resources/Get-AzResourceGroupDeploymentStack>