



Windows PowerShell Get-Help on Cmdlet 'Get-AzResourceMoverMoveCollection'

PS:\>Get-HELP Get-AzResourceMoverMoveCollection -Full

NAME

Get-AzResourceMoverMoveCollection

SYNOPSIS

Gets the move collection.

****The 'Get-AzResourceMoverMoveCollection' command remains same for both 'RegionToRegion' and 'RegionToZone' type move collections.****

SYNTAX

Get-AzResourceMoverMoveCollection [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]

Get-AzResourceMoverMoveCollection -Name <String> -ResourceGroupName <String> [-SubscriptionId <String[]>]
[-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend
<SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]

```
Get-AzResourceMoverMoveCollection -ResourceGroupName <String> [-SubscriptionId <String[]>] [-DefaultProfile
<PSObject>] [-Break] [-HttpPipelineAppend
<SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Gets the move collection.

****The 'Get-AzResourceMoverMoveCollection' command remains same for both 'RegionToRegion' and 'RegionToZone' type move collections.****

PARAMETERS

-Name <String>

The Move Collection Name.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The Resource Group Name.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The Subscription ID.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.ResourceMover.Models.Api20230801.IMoveCollection

----- EXAMPLE 1 -----

```
PS C:\>Get-AzResourceMoverMoveCollection -SubscriptionId "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx"
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzResourceMoverMoveCollection -ResourceGroupName "RG-MoveCollection-demoRMS" -Name "PS-centralus-westcentralus-demoRMS"
```

----- EXAMPLE 3 -----

```
PS C:\>Get-AzResourceMoverMoveCollection -ResourceGroupName "RG-MoveCollection-demoRMS"
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.resourcemover/get-azresourcemovermovecollection>