



Windows PowerShell Get-Help on Cmdlet 'Get-AzResourceMoverUnresolvedDependency'

PS:\>Get-HELP Get-AzResourceMoverUnresolvedDependency -Full

NAME

Get-AzResourceMoverUnresolvedDependency

SYNOPSIS

Gets a list of unresolved dependencies.

****The 'Get-AzResourceMoverUnresolvedDependency' command is applicable for 'RegionToRegion' type move collections.****

****However, for move collections with moveType 'RegionToZone' dependencies are automatically added to the move collection once**

'Resolve-AzResourceMoverMoveCollectionDependency' is executed.

Please refer to 'Resolve-AzResourceMoverMoveCollectionDependency' command documentation for additional details.**

SYNTAX

Get-AzResourceMoverUnresolvedDependency -MoveCollectionName <String> -ResourceGroupName <String>
[-SubscriptionId <String>] [-DependencyLevel <DependencyLevel>]
[-Filter <String>] [-OrderBy <String>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep>]
[-HttpPipelinePrepend <SendAsyncStep>] [-Proxy

<Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [<CommonParameters>]

DESCRIPTION

Gets a list of unresolved dependencies.

****The 'Get-AzResourceMoverUnresolvedDependency' command is applicable for 'RegionToRegion' type move collections.****

****However, for move collections with moveType 'RegionToZone' dependencies are automatically added to the move collection once**

'Resolve-AzResourceMoverMoveCollectionDependency' is executed.

Please refer to 'Resolve-AzResourceMoverMoveCollectionDependency' command documentation for additional details.**

PARAMETERS

-MoveCollectionName <String>

The Move Collection Name.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The Resource Group Name.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The Subscription ID.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DependencyLevel <DependencyLevel>

Defines the dependency level.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Filter <String>

The filter to apply on the operation.

For example, \$apply=filter(count eq 2).

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-OrderBy <String>

OData order by query option.

For example, you can use \$orderby=Count desc.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.ResourceMover.Models.Api20230801.IUnresolvedDependency

----- EXAMPLE 1 -----

```
PS C:\>Get-AzResourceMoverUnresolvedDependency -MoveCollectionName "PS-centralus-westcentralus-demoRMS"
-ResourceGroupName "RG-MoveCollection-demoRMS"
-DependencyLevel Descendant
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.resourcemover/get-azresourcemoverunresolveddependency>