



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Get-AzRouteConfig'***

**PS:\>Get-HELP Get-AzRouteConfig -Full**

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

#### **NAME**

Get-AzRouteConfig

#### **SYNOPSIS**

Gets routes from a route table.

#### **SYNTAX**

Get-AzRouteConfig

[-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]

[-Name

<System.String>] -RouteTable

<Microsoft.Azure.Commands.Network.Models.PSRouteTable> [<CommonParameters>]

#### **DESCRIPTION**

The Get-AzRouteConfig cmdlet gets routes from an Azure route table. You can specify a route by name.

Page 1/4

## PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the route that this cmdlet gets.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-RouteTable <Microsoft.Azure.Commands.Network.Models.PSRouteTable>

Specifies the route table from which this cmdlet gets routes.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

`OutBuffer`, `PipelineVariable`, and `OutVariable`. For more information, see [about\\_CommonParameters](#) (<https://go.microsoft.com/fwlink/?LinkId=113216>).

## INPUTS

`Microsoft.Azure.Commands.Network.Models.PSRouteTable`

## OUTPUTS

`Microsoft.Azure.Commands.Network.Models.PSRoute`

## NOTES

----- Example 1: Get a route table -----

```
Get-AzRouteTable -ResourceGroupName "ResourceGroup11" -Name "RouteTable01" | Get-AzRouteConfig -Name "Route07"
```

Name : route07

Id :

Etag :

ProvisioningState :

AddressPrefix : 10.1.0.0/16

NextHopType : VnetLocal

NextHopIpAddress :

This command gets the route table named `RouteTable01` by using the `Get-AzRouteTable` cmdlet. The command passes that table to the current cmdlet by using the pipeline

operator. The current cmdlet gets the route named Route07 in the route table named RouteTable01.

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/get-azrouteconfig>

[Add-AzRouteConfig](#)

[Get-AzRouteTable](#)

[New-AzRouteConfig](#)

[Remove-AzRouteConfig](#)

[Set-AzRouteConfig](#)