



Windows PowerShell Get-Help on Cmdlet 'Get-AzServiceBusPrivateEndpointConnection'

PS:\>Get-HELP Get-AzServiceBusPrivateEndpointConnection -Full

NAME

Get-AzServiceBusPrivateEndpointConnection

SYNOPSIS

Gets a description for the specified Private Endpoint Connection.

SYNTAX

```
Get-AzServiceBusPrivateEndpointConnection -NamespaceName <String> -ResourceGroupName <String>
[-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
<PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]
```

```
Get-AzServiceBusPrivateEndpointConnection -Name <String> -NamespaceInputObject <IServiceBusIdentity>
[-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend
<SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzServiceBusPrivateEndpointConnection -Name <String> -NamespaceName <String> -ResourceGroupName
```

```
<String> [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>]
    [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>]
    [-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzServiceBusPrivateEndpointConnection -InputObject <IServiceBusIdentity> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
    [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Gets a description for the specified Private Endpoint Connection.

PARAMETERS

-Name <String>

The PrivateEndpointConnection name

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NamespaceName <String>

The namespace name

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

Name of the Resource group within the Azure subscription.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

Subscription credentials that uniquely identify a Microsoft Azure subscription.

The subscription ID forms part of the URI for every service call.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IServiceBusIdentity>

Identity Parameter

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-NamespaceInputObject <IServiceBusIdentity>

Identity Parameter

Required? true

Position? named
Default value
Accept pipeline input? true (ByValue)
Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.
Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.ServiceBus.Models.IServiceBusIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.ServiceBus.Models.IPrivateEndpointConnection

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

[about_Hash_Tables](#).

INPUTOBJECT <IServiceBusIdentity>: Identity Parameter

[Alias <String>]: The Disaster Recovery configuration name

[AuthorizationRuleName <String>]: The authorization rule name.

[ConfigName <String>]: The configuration name. Should always be "\$default".

[Id <String>]: Resource identity path

[NamespaceName <String>]: The namespace name

[PrivateEndpointConnectionName <String>]: The PrivateEndpointConnection name

[QueueName <String>]: The queue name.

[ResourceGroupName <String>]: Name of the Resource group within the Azure subscription.

[RuleName <String>]: The rule name.

[SubscriptionId <String>]: Subscription credentials that uniquely identify a Microsoft Azure subscription. The subscription ID forms part of the URI for every

service call.

[SubscriptionName <String>]: The subscription name.

[TopicName <String>]: The topic name.

NAMESPACEINPUTOBJECT <IServiceBusIdentity>: Identity Parameter

[Alias <String>]: The Disaster Recovery configuration name

[AuthorizationRuleName <String>]: The authorization rule name.

[ConfigName <String>]: The configuration name. Should always be "\$default".

[Id <String>]: Resource identity path

[NamespaceName <String>]: The namespace name

[PrivateEndpointConnectionName <String>]: The PrivateEndpointConnection name

[QueueName <String>]: The queue name.

[ResourceGroupName <String>]: Name of the Resource group within the Azure subscription.

[RuleName <String>]: The rule name.

[SubscriptionId <String>]: Subscription credentials that uniquely identify a Microsoft Azure subscription. The subscription ID forms part of the URI for every

service call.

[SubscriptionName <String>]: The subscription name.

[TopicName <String>]: The topic name.

----- EXAMPLE 1 -----

```
PS C:\>Get-AzServiceBusPrivateEndpointConnection -ResourceGroupName myResourceGroup -NamespaceName myNamespace -Name 000000000000
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzServiceBusPrivateEndpointConnection -ResourceGroupName myResourceGroup -NamespaceName  
myNamespace
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.servicebus/get-azservicebusprivateendpointconnection>

<https://msdn.microsoft.com/en-us/library/azure/mt639379.aspx>

<https://msdn.microsoft.com/en-us/library/azure/mt639412.aspx>