



Windows PowerShell Get-Help on Cmdlet 'Get-AzSqlElasticJobStep'

PS:\>Get-HELP Get-AzSqlElasticJobStep -Full

NAME

Get-AzSqlElasticJobStep

SYNOPSIS

Gets one or more job steps

SYNTAX

```
Get-AzSqlElasticJobStep [-ResourceGroupName] <System.String> [-ServerName] <System.String> [-AgentName]
<System.String> [-JobName] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
<System.String>] [<CommonParameters>]
```

```
Get-AzSqlElasticJobStep [-ResourceGroupName] <System.String> [-ServerName] <System.String> [-AgentName]
<System.String> [-JobName] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
<System.String> -Version <System.Nullable`1[System.Int32]>
[<CommonParameters>]
```

```
Get-AzSqlElasticJobStep [-ParentObject] <Microsoft.Azure.Commands.Sql.ElasticJobs.Model.AzureSqlElasticJobModel>
```

[-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name

<System.String>] [<CommonParameters>]

Get-AzSqlElasticJobStep [-ParentResourceId] <System.String> [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name

<System.String>] [<CommonParameters>]

Get-AzSqlElasticJobStep [-ParentObject] <Microsoft.Azure.Commands.Sql.ElasticJobs.Model.AzureSqlElasticJobModel>

[-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name

<System.String> -Version <System.Nullable`1[System.Int32]>

[<CommonParameters>]

Get-AzSqlElasticJobStep [-ParentResourceId] <System.String> [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name

<System.String> -Version <System.Nullable`1[System.Int32]>

[<CommonParameters>]

DESCRIPTION

The Get-AzSqlElasticJobStep cmdlet gets one or more job steps from a job

PARAMETERS

-AgentName <System.String>

The agent name

Required? true

Position? 2

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-JobName <System.String>

The job name

Required? true

Position? 3

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The job step name

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ParentObject <Microsoft.Azure.Commands.Sql.ElasticJobs.Model.AzureSqlElasticJobModel>

The job input object

Required? true

Position? 0

Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-ParentResourceId <System.String>

The job resource id

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name

Required? true
Position? 0
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ServerName <System.String>

The server name

Required? true
Position? 1
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Version <System.Nullable`1[System.Int32]>

The job step name

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByPropertyName)
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Sql.ElasticJobs.Model.AzureSqlElasticJobModel

OUTPUTS

Microsoft.Azure.Commands.Sql.ElasticJobs.Model.AzureSqlElasticJobStepModel

NOTES

----- Example 1: Gets a job step from a job -----

```
$job = Get-AzSqlElasticJob -ResourceGroupName rg -ServerName elasticjobserver -AgentName agent -Name job1  
$job | Get-AzSqlElasticJobStep -Name step1
```

JobName	StepName	StepId	TargetGroupName	CredentialName	Output	ExecutionOptions	CommandText
---------	----------	--------	-----------------	----------------	--------	------------------	-------------

job1	step1	1	tg1	cred1	(43200,10,1,120,2)	SELECT 1	
------	-------	---	-----	-------	--------------------	----------	--

Gets a job step from a job

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/Az.sql/get-Azsqlelasticjobstep>