



Windows PowerShell Get-Help on Cmdlet 'Get-AzSqlServerDisasterRecoveryConfiguration'

PS:\>Get-HELP Get-AzSqlServerDisasterRecoveryConfiguration -Full

NAME

Get-AzSqlServerDisasterRecoveryConfiguration

SYNOPSIS

Gets a database server system recovery configuration.

SYNTAX

```
Get-AzSqlServerDisasterRecoveryConfiguration [-ResourceGroupName] <System.String> [-ServerName]
<System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-VirtualEndpointName <System.String>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

The Get-AzSqlServerDisasterRecoveryConfiguration cmdlet gets a SQL database server system recovery configuration.

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ServerName <System.String>

Specifies the name of SQL database server.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-VirtualEndpointName <System.String>

Specifies the name of the virtual end point.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? true

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Sql.ServerDisasterRecoveryConfiguration.Model.AzureSqlServerDisasterRecoveryConfigurationModel

NOTES

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/get-azsqlserverdisasterrecoveryconfiguration>

[New-AzSqlServerDisasterRecoveryConfiguration](#)

[Remove-AzSqlServerDisasterRecoveryConfiguration](#)

[Set-AzSqlServerDisasterRecoveryConfiguration](#)

SQL Database Documentation <https://learn.microsoft.com/azure/sql-database/>