



Windows PowerShell Get-Help on Cmdlet 'Get-AzStaticWebAppUser'

PS:\>Get-HELP Get-AzStaticWebAppUser -Full

NAME

Get-AzStaticWebAppUser

SYNOPSIS

Description for Gets the list of users of a static site.

SYNTAX

```
Get-AzStaticWebAppUser -AuthProvider <String> -Name <String> -ResourceGroupName <String> [-SubscriptionId  
<String[]>] [-DefaultProfile <PSObject>] [-Break]  
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential  
<PSCredential>] [-ProxyUseDefaultCredentials]  
[-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Description for Gets the list of users of a static site.

PARAMETERS

-AuthProvider <String>

The auth provider for the users.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Name <String>

Name of the static site.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

Name of the resource group to which the resource belongs.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

Your Azure subscription ID.

This is a GUID-formatted string (e.g.

00000000-0000-0000-0000-000000000000).

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false
Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Websites.Models.Api20201201.IStaticSiteUserArmResource

----- EXAMPLE 1 -----

```
PS C:\>Get-AzStaticWebAppUser -ResourceGroupName azure-rg-test -Name staticweb-portal04 -Authprovider all
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.websites/get-azstaticwebappuser>