



Windows PowerShell Get-Help on Cmdlet 'Get-AzStorageSyncServerEndpoint'

PS:\>Get-HELP Get-AzStorageSyncServerEndpoint -Full

NAME

Get-AzStorageSyncServerEndpoint

SYNOPSIS

This command lists all server endpoints within a given sync group.

SYNTAX

```
Get-AzStorageSyncServerEndpoint [-ParentObject] <Microsoft.Azure.Commands.StorageSync.Models.PSSyncGroup>
[-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
    <System.String>] [<CommonParameters>]
```

```
Get-AzStorageSyncServerEndpoint [-ParentResourceId] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
    <System.String>] [<CommonParameters>]
```

```
Get-AzStorageSyncServerEndpoint [-ResourceGroupName] <System.String> [-StorageSyncServiceName]
<System.String> [-SyncGroupName] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
```

<System.String>] [<CommonParameters>]

DESCRIPTION

This command lists all server endpoints within a given sync group. It can be used to also list the attributes of each server endpoint.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Name of the server endpoint.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ParentObject <Microsoft.Azure.Commands.StorageSync.Models.PSSyncGroup>

StorageSyncService Object, normally passed through the parameter.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-ParentResourceId <System.String>

StorageSyncService Object, normally passed through the parameter.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-StorageSyncServiceName <System.String>

Name of the StorageSyncService.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-SyncGroupName <System.String>

Name of the SyncGroup.

Required? true
Position? 2
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.StorageSync.Models.PSSyncGroup

System.String

OUTPUTS

Microsoft.Azure.Commands.StorageSync.Models.PSServerEndpoint

NOTES

----- Example 1 -----

```
"myStorageSyncServiceName" -SyncGroupName "mySyncGroupName"
```

This command gets all server endpoints contained within the specified sync group. Specify -ServerEndpointName to return a specific one.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/Az.storagesync/get-Azstoragesyncserverendpoint>