



Windows PowerShell Get-Help on Cmdlet 'Get-AzStreamAnalyticsDefaultFunctionDefinition'

PS:\>Get-HELP Get-AzStreamAnalyticsDefaultFunctionDefinition -Full

NAME

Get-AzStreamAnalyticsDefaultFunctionDefinition

SYNOPSIS

Retrieves the default definition of a function based on the parameters specified.

SYNTAX

```
Get-AzStreamAnalyticsDefaultFunctionDefinition -Name <String> -JobName <String> -ResourceGroupName <String>  
-BindingType <String> -Endpoint <String> -UdfType <String>  
[-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]  
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]  
[-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Retrieves the default definition of a function based on the parameters specified.

-Name <String>

The name of the function.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-JobName <String>

The name of the streaming job.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-BindingType <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Endpoint <String>

The name of the resource group.
The name is case insensitive.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-UdfType <String>

The name of the resource group.
The name is case insensitive.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.StreamAnalytics.Models.Api20170401Preview.IFunctionRetrieveDefaultDefinitionParameters

Microsoft.Azure.PowerShell.Cmdlets.StreamAnalytics.Models.IStreamAnalyticsIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.StreamAnalytics.Models.Api20170401Preview.IFunction

```
PS C:\>Get-AzStreamAnalyticsDefaultFunctionDefinition -ResourceGroupName azure-rg-test -JobName sajob-01-pwsh  
-Name mlsfunction-01 -BindingType  
Microsoft.MachineLearningServices -Endpoint  
"http://875da830-4d5f-44f1-b221-718a5f26a21d.eastus.azurecontainer.io/score"-UdfType Scalar
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.streamanalytics/get-azstreamanalyticsdefaultfunctiondefinition>