



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Get-AzSubscriptionDeploymentStack'***

**PS:\>Get-HELP Get-AzSubscriptionDeploymentStack -Full**

#### **NAME**

Get-AzSubscriptionDeploymentStack

#### **SYNOPSIS**

Gets Subscription scoped Deployment Stacks.

#### **SYNTAX**

Get-AzSubscriptionDeploymentStack [-Name] <System.String> [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]

[-Pre] [<CommonParameters>]

Get-AzSubscriptionDeploymentStack [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Pre] -ResourceId

<System.String> [<CommonParameters>]

#### **DESCRIPTION**

Retrieve a subscription scoped deployment stack.

## PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The name of the DeploymentStack to get

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Pre <System.Management.Automation.SwitchParameter>

When set, indicates that the cmdlet should use pre-release API versions when automatically determining which version to use.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Resourceld <System.String>

Resourceld of the DeploymentStack to get

Required? true  
Position? named  
Default value None  
Accept pipeline input? True (ByPropertyName)  
Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

#### INPUTS

System.String

#### OUTPUTS

Microsoft.Azure.Commands.ResourceManager.Cmdlets.SdkModels.PSDeploymentStack

#### NOTES

Example 1: Retrieve a stack named MySubStack from the current subscription

```
Get-AzSubscriptionDeploymentStack -Name MySubStack
```

Get a deployment stack named 'MySubStack' under the default subscription.

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.resources/Get-AzSubscriptionDeploymentStack>