



Windows PowerShell Get-Help on Cmdlet 'Get-AzSynapseActiveDirectoryOnlyAuthentication'

PS: \>Get-HELP Get-AzSynapseActiveDirectoryOnlyAuthentication -Full

NAME

Get-AzSynapseActiveDirectoryOnlyAuthentication

SYNOPSIS

Gets Microsoft Entra-only authentication for a specific Synapse workspace.

SYNTAX

```
Get-AzSynapseActiveDirectoryOnlyAuthentication [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[-ResourceGroupName <System.String>] -WorkspaceName <System.String> [<CommonParameters>]
```

```
Get-AzSynapseActiveDirectoryOnlyAuthentication [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -ResourceId
<System.String> [<CommonParameters>]
```

```
Get-AzSynapseActiveDirectoryOnlyAuthentication [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace> [<CommonParameters>]
```

DESCRIPTION

The `Get-AzSynapseActiveDirectoryOnlyAuthentication` cmdlet gets Microsoft Entra-only authentication for a specific Synapse workspace.

PARAMETERS

`-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>`

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-ResourceGroupName <System.String>`

Resource group name.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-ResourceId <System.String>`

Resource identifier of Synapse workspace.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceName <System.String>

Name of Synapse workspace.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

workspace input object, usually passed through the pipeline.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace

OUTPUTS

Microsoft.Azure.Commands.Synapse.Models.PSAzureADOnlyAuthentication

NOTES

----- Example 1 -----

```
Get-AzSynapseActiveDirectoryOnlyAuthentication -WorkspaceName ContosoWorkspace
```

WorkspaceName	AzureADOnlyAuthenticationProperty	State	CreationDate
---------------	-----------------------------------	-------	--------------

-----	-----	-----	-----
-------	-------	-------	-------

ContosoWorkspace	True	Consistent	3/23/2022 8:27:47 AM
------------------	------	------------	----------------------

This command gets Microsoft Entra-only authentication status for Synapse workspace ContosoWorkspace.

----- Example 2 -----

```
$ws = Get-AzSynapseWorkspace -Name ContosoWorkspace
```

```
$ws | Get-AzSynapseActiveDirectoryOnlyAuthentication
```

WorkspaceName	AzureADOnlyAuthenticationProperty	State	CreationDate
---------------	-----------------------------------	-------	--------------

-----	-----	-----	-----
-------	-------	-------	-------

ContosoWorkspace	True	Consistent	3/23/2022 8:27:47 AM
------------------	------	------------	----------------------

This command gets Microsoft Entra-only authentication status for Synapse workspace ContosoWorkspace through pipeline.

----- Example 3 -----

Get-AzSynapseActiveDirectoryOnlyAuthentication -ResourceId

/subscriptions/21686af7-58ec-4f4d-9c68-f431f4db4edd/resourceGroups/ContosoResourceGroup/providers/Microsoft.Synapse/workspaces/ContosoWorkspace

WorkspaceName	AzureADOnlyAuthenticationProperty	State	CreationDate
-----	-----	-----	-----
ContosoWorkspace	True	Consistent	3/23/2022 8:27:47 AM

This command gets Microsoft Entra-only authentication for workspace ContosoWorkspace by ResourceId.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.synapse/get-azsynapseactivedirectoryonlyauthentication>