



Windows PowerShell Get-Help on Cmdlet 'Get-AzSynapseKustoPoolSku'

PS: \>Get-HELP Get-AzSynapseKustoPoolSku -Full

NAME

Get-AzSynapseKustoPoolSku

SYNOPSIS

Lists eligible SKUs for Kusto Pool resource.

SYNTAX

```
Get-AzSynapseKustoPoolSku [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend  
<SendAsyncStep[]>] [-HttpPipelinePrepend  
    <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]  
[<CommonParameters>]
```

```
Get-AzSynapseKustoPoolSku [-SubscriptionId <String[]>] -KustoPoolName <String> -ResourceGroupName <String>  
-WorkspaceName <String> [-DefaultProfile <PSObject>]  
    [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]  
[-ProxyCredential <PSCredential>]  
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

Lists eligible SKUs for Kusto Pool resource.

PARAMETERS

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-KustoPoolName <String>

The name of the Kusto pool.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-WorkspaceName <String>

The name of the workspace

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Synapse.Models.Api20210601Preview.IAzureResourceSku

Microsoft.Azure.PowerShell.Cmdlets.Synapse.Models.Api20210601Preview.ISkuDescription

----- EXAMPLE 1 -----

PS C:\>Get-AzSynapseKustoPoolSku

----- EXAMPLE 2 -----

PS C:\>Get-AzSynapseKustoPoolSku -ResourceGroupName testrg -WorkspaceName testws -KustoPoolName

testnewkustopool

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.synapse/get-azsynapsekustopoolsku>