



Windows PowerShell Get-Help on Cmdlet 'Get-AzSynapseLinkConnection'

PS:\>Get-HELP Get-AzSynapseLinkConnection -Full

NAME

Get-AzSynapseLinkConnection

SYNOPSIS

Gets information about link connections in workspace.

SYNTAX

```
Get-AzSynapseLinkConnection [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name  
<System.String>]  
-WorkspaceName <System.String> [<CommonParameters>]
```

```
Get-AzSynapseLinkConnection [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name  
<System.String>]  
-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace> [<CommonParameters>]
```

DESCRIPTION

The Get-AzSynapseLinkConnection cmdlet gets information about link connections in a workspace. If you specify the name of a link connection, the cmdlet gets

information about that link connection. If you do not specify a name, the cmdlet gets information about all link connections in the workspace.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The Synapse link connection name for Azure Sql Database.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceName <System.String>

Name of Synapse workspace.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>
workspace input object, usually passed through the pipeline.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace

OUTPUTS

Microsoft.Azure.Commands.Synapse.Models.PSLinkConnectionResource

NOTES

----- Example 1 -----

```
Get-AzSynapseLinkConnection -WorkspaceName ContosoWorkspace
```

Gets a list of all link connections in the workspace ContosoWorkspace.

----- Example 2 -----

```
Get-AzSynapseLinkConnection -WorkspaceName ContosoWorkspace -Name ContosoLinkConnection
```

Gets a single link connection named ContosoLinkConnection in the workspace ContosoWorkspace.

----- Example 3 -----

```
$ws = Get-AzSynapseWorkspace -Name ContosoWorkspace
```

```
$ws | Get-AzSynapseLinkConnection
```

This command gets all link connections under a workspace through pipeline.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.synapse/get-azsynapselinkconnection>