



Windows PowerShell Get-Help on Cmdlet 'Get-AzSynapseSparkConfiguration'

PS:\>Get-HELP Get-AzSynapseSparkConfiguration -Full

NAME

Get-AzSynapseSparkConfiguration

SYNOPSIS

Gets information about spark configurations in a workspace.

SYNTAX

```

Get-AzSynapseSparkConfiguration [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
<System.String>]
-WorkspaceName <System.String> [<CommonParameters>]
```

```

Get-AzSynapseSparkConfiguration [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Name
<System.String>]
-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace> [<CommonParameters>]
```

DESCRIPTION

The Get-AzSynapseSparkConfiguration cmdlet gets information about spark configurations in a workspace. If you specify the name of a spark configuration, the cmdlet

gets information about that spark configuration. If you do not specify a name, the cmdlet gets information about all spark configurations in the workspace.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The Spark Configuration name.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceName <System.String>

Name of Synapse workspace.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>
workspace input object, usually passed through the pipeline.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace

OUTPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSparkConfigurationResource

NOTES

----- Example 1 -----

Get-AzSynapseSparkConfiguration -WorkspaceName ContosoWorkspace

Gets a list of all spark configurations in the workspace ContosoWorkspace.

----- Example 2 -----

Get-AzSynapseSparkConfiguration -WorkspaceName ContosoWorkspace -Name ContosoSparkConfiguration

Gets a single spark configuration called ContosoSparkConfiguration in the workspace ContosoWorkspace.

----- Example 3 -----

\$ws = Get-AzSynapseWorkspace -Name ContosoWorkspace

\$ws | Get-AzSynapseSparkConfiguration -Name ContosoSparkConfiguration

Gets a single spark configuration called ContosoSparkConfiguration in the workspace ContosoWorkspace through pipeline.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.synapse/get-azsynapsesparkconfiguration>