



Windows PowerShell Get-Help on Cmdlet 'Get-AzSynapseTriggerSubscriptionStatus'

PS: \>Get-HELP Get-AzSynapseTriggerSubscriptionStatus -Full

NAME

Get-AzSynapseTriggerSubscriptionStatus

SYNOPSIS

Get the status of the subscription for the event trigger to the specified external service events.

SYNTAX

Get-AzSynapseTriggerSubscriptionStatus [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject

<Microsoft.Azure.Commands.Synapse.Models.PSTriggerResource> [<CommonParameters>]

Get-AzSynapseTriggerSubscriptionStatus [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name

<System.String> -WorkspaceName <System.String> [<CommonParameters>]

Get-AzSynapseTriggerSubscriptionStatus [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name

<System.String> -WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

[<CommonParameters>]

DESCRIPTION

The Get-AzSynapseTriggerSubscriptionStatus cmdlet gets the status of the subscription for the event trigger to the specified external service events. The trigger

can't be started until the returned status is "Enabled".

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Synapse.Models.PSTriggerResource>

The trigger object.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The trigger name.

Required? true

Position? named

Default value None

Accept pipeline input? False
Accept wildcard characters? false

-WorkspaceName <System.String>

Name of Synapse workspace.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

workspace input object, usually passed through the pipeline.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace

Microsoft.Azure.Commands.Synapse.Models.PSTriggerResource

OUTPUTS

Microsoft.Azure.Commands.Synapse.Models.PSTriggerSubscriptionOperationStatus

NOTES

----- Example 1 -----

```
Get-AzSynapseTriggerSubscriptionStatus -WorkspaceName ContosoWorkspace -Name ContosoTrigger
```

This command will get the status of the subscription for trigger called ContosoTrigger to the external service events.

----- Example 2 -----

```
$ws = Get-AzSynapseWorkspace -Name ContosoWorkspace
```

```
$ws | Get-AzSynapseTriggerSubscriptionStatus -Name ContosoTrigger
```

This command will get the status of the subscription for trigger called ContosoTrigger to the external service events through pipeline.

----- Example 3 -----

```
$trigger = Get-AzSynapseTrigger -WorkspaceName ContosoWorkspace -Name ContosoTrigger
```

```
$trigger | Get-AzSynapseTriggerSubscriptionStatus
```

This command will get the status of the subscription for trigger called ContosoTrigger to the external service events through pipeline.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.synapse/get-azsynapsetriggerstatus>