



Windows PowerShell Get-Help on Cmdlet 'Get-AzWvdPrivateLinkResource'

PS:\>Get-HELP Get-AzWvdPrivateLinkResource -Full

NAME

Get-AzWvdPrivateLinkResource

SYNOPSIS

List the private link resources available for this workspace.

SYNTAX

```
Get-AzWvdPrivateLinkResource -ResourceGroupName <String> [-SubscriptionId <String[]>] -WorkspaceName <String>
[-InitialSkip <Int32>] [-IsDescending] [-PageSize
    <Int32>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
    <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
    <PSCredential>] [-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzWvdPrivateLinkResource -ResourceGroupName <String> [-SubscriptionId <String[]>] -HostPoolName <String>
[-InitialSkip <Int32>] [-IsDescending] [-PageSize
    <Int32>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
    <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
    <PSCredential>] [-ProxyUseDefaultCredentials] [<CommonParameters>]
```

DESCRIPTION

List the private link resources available for this workspace.

PARAMETERS

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-WorkspaceName <String>

The name of the workspace

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HostPoolName <String>

The name of the host pool within the specified resource group

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InitialSkip <Int32>

Initial number of items to skip.

Required? false

Position? named

Default value 0

Accept pipeline input? false

Accept wildcard characters? false

-IsDescending [<SwitchParameter>]

Indicates whether the collection is descending.

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-PageSize <Int32>

Number of items per page.

Required? false

Position? named

Default value 0
Accept pipeline input? false
Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.DesktopVirtualization.Models.Api20230905.IPrivateLinkResource

----- EXAMPLE 1 -----

```
PS C:\>Get-AzWvdPrivateLinkResource -ResourceGroupName ResourceGroupName -WorkspaceName workspaceName
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzWvdPrivateLinkResource -ResourceGroupName ResourceGroupName -HostPoolName hostpoolName
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.desktopvirtualization/get-azwvdprivatelinkresource>