



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Get-NetIPConfiguration'

PS:\>Get-HELP Get-NetIPConfiguration -Full

NAME

Get-NetIPConfiguration

SYNOPSIS

SYNTAX

```
Get-NetIPConfiguration [[-InterfaceAlias] <String>] [-AllCompartments] [-CompartmentId <Int32>] [-Detailed]
[-CimSession <CimSession>] [<CommonParameters>]
```

```
Get-NetIPConfiguration -InterfaceIndex <Int32> [-AllCompartments] [-CompartmentId <Int32>] [-Detailed] [-CimSession
<CimSession>] [<CommonParameters>]
```

```
Get-NetIPConfiguration -All [-AllCompartments] [-CompartmentId <Int32>] [-Detailed] [-CimSession <CimSession>]
[<CommonParameters>]
```

DESCRIPTION

PARAMETERS

-InterfaceAlias <String>

Required? false

Position? 1

Default value *

Accept pipeline input? true (ByPropertyName)

Accept wildcard characters? false

-InterfaceIndex <Int32>

Required? true

Position? named

Default value -1

Accept pipeline input? true (ByPropertyName)

Accept wildcard characters? false

-All [<SwitchParameter>]

Required? true

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-AllCompartments [<SwitchParameter>]

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-CompartmentId <Int32>

Required? false
Position? named
Default value -1
Accept pipeline input? true (ByPropertyName)
Accept wildcard characters? false

-Detailed [<SwitchParameter>]

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-CimSession <CimSession>

Required? false
Position? named
Default value
Accept pipeline input? true (ByPropertyName)
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

INPUTS

OUTPUTS

RELATED LINKS

<http://go.microsoft.com/fwlink/?LinkId=253567>