



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Get-RunspaceDebug'***

**PS:\>Get-HELP Get-RunspaceDebug -Full**

#### **NAME**

Get-RunspaceDebug

#### **SYNOPSIS**

Shows runspace debugging options.

#### **SYNTAX**

Get-RunspaceDebug [[-ProcessName] <System.String>] [[-AppDomainName] <System.String[]>]

[<CommonParameters>]

Get-RunspaceDebug [-Runspace] <System.Management.Automation.Runspaces.Runspace[]> [<CommonParameters>]

Get-RunspaceDebug [-RunspaceId] <System.Int32[]> [<CommonParameters>]

Get-RunspaceDebug [-RunspaceInstanceId] <System.Guid[]> [<CommonParameters>]

Get-RunspaceDebug [[-RunspaceName] <System.String[]>] [<CommonParameters>]

## DESCRIPTION

The `Get-RunspaceDebug` cmdlet shows runspace debugging options.

## PARAMETERS

-AppDomainName <System.String[]>

The name of the application domain that hosts the PowerShell runspace.

Required?                false

Position?                1

Default value            None

Accept pipeline input?   False

Accept wildcard characters?   false

-ProcessName <System.String>

The name of the process that hosts the PowerShell runspace.

Required?                false

Position?                0

Default value            None

Accept pipeline input?   False

Accept wildcard characters?   false

-Runspace <System.Management.Automation.Runspaces.Runspace[]>

One or more Runspace objects to be disabled.

Required?                true

Position?                0

Default value            None

Accept pipeline input?   True (ByPropertyName, ByValue)

Accept wildcard characters?   false

-RunspaceId <System.Int32[]>

One or more Runspace Id numbers to be disabled.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

#### -RunspaceInstanceId <System.Guid[]>

One or more Runspace GUIDs to be disabled.

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

#### -RunspaceName <System.String[]>

One or more Runspace names to be disabled.

Required? false

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## OUTPUTS

## NOTES

----- 1: Show the state of the default runspace debugger -----

`Get-RunspaceDebug`

Id	Name	Enabled	BreakAll
1	Runspace1	False	False

## RELATED LINKS

Online

Version:

[https://learn.microsoft.com/powershell/module/microsoft.powershell.utility/get-runspacedebug?view=powershell-5.1&WT.mc\\_id=ps-gethelp](https://learn.microsoft.com/powershell/module/microsoft.powershell.utility/get-runspacedebug?view=powershell-5.1&WT.mc_id=ps-gethelp)

`Disable-RunspaceDebug`

`Enable-RunspaceDebug`