



### ***Windows PowerShell Get-Help on Cmdlet 'Get-VpnConnectionTrigger'***

***PS:\>Get-HELP Get-VpnConnectionTrigger -Full***

#### NAME

Get-VpnConnectionTrigger

#### SYNOPSIS

Gets trigger properties of a VPN connection.

#### SYNTAX

Get-VpnConnectionTrigger [-ConnectionName] <String> [-AsJob] [-CimSession <CimSession[]>] [-ThrottleLimit <Int32>]  
[<CommonParameters>]

#### DESCRIPTION

The Get-VpnConnectionTrigger cmdlet gets trigger properties of a virtual private network (VPN) connection.

#### PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

Required? false  
Position? named  
Default value False  
Accept pipeline input? False  
Accept wildcard characters? false

**-CimSession <CimSession[]>**

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a New-CimSession

(<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or

[Get-CimSession](<https://go.microsoft.com/fwlink/p/?LinkId=227966>)cmdlet. The default is the current session on the local computer.

Required? false  
Position? named  
Default value None  
Accept pipeline input? False  
Accept wildcard characters? false

**-ConnectionName <String>**

Specifies the name of a VPN connection profile. To view existing VPN connection profiles, use the Get-VpnConnection cmdlet.

Required? true  
Position? 1  
Default value None  
Accept pipeline input? True (ByPropertyName)  
Accept wildcard characters? false

**-ThrottleLimit <Int32>**

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then

Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are

running on the computer. The throttle limit

applies only to the current cmdlet, not to the session or to the computer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

#### INPUTS

#### OUTPUTS

Microsoft.Management.Infrastructure.CimInstance#VpnConnectionTrigger

#### NOTES

---- Example 1: Get trigger properties of a VPN connection ----

```
PS C:\> Get-VpnConnectionTrigger -ConnectionName "ContosoVPN"
```

```
ConnectionName: Contoso
```

```
C:\Windows\System32\WindowsPowerShell\v1.0\powershell.exe}
```

```
TrustedNetwork: {newyork.contoso.com, washington.contoso.com}
```

This command gets the trigger properties of the VPN connection named ContosoVPN.

## RELATED LINKS

Online

Version:

[https://learn.microsoft.com/powershell/module/vpnclient/get-vpnconnectiontrigger?view=windowsserver2022-ps&wt.mc\\_id=ps-gethelp](https://learn.microsoft.com/powershell/module/vpnclient/get-vpnconnectiontrigger?view=windowsserver2022-ps&wt.mc_id=ps-gethelp)

Get-VpnConnection