



Windows PowerShell Get-Help on Cmdlet 'Import-AzAksCredential'

PS:\>Get-HELP Import-AzAksCredential -Full

NAME

Import-AzAksCredential

SYNOPSIS

Import and merge Kubectl config for a managed Kubernetes Cluster.

SYNTAX

Import-AzAksCredential [-Id] <System.String> [-Admin] [-ConfigPath <System.String>] [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]

[-PublicFqdn] [-SubscriptionId <System.String>]

[-Confirm] [-WhatIf] [<CommonParameters>]

Import-AzAksCredential [-Admin] [-ConfigPath <System.String>] [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -InputObject

<Microsoft.Azure.Commands.Aks.Models.PSKubernetesCluster> [-PassThru] [-PublicFqdn] [-SubscriptionId

<System.String>] [-Confirm] [-WhatIf] [<CommonParameters>]

Import-AzAksCredential [-ResourceGroupName] <System.String> [-Name] <System.String> [-Admin] [-ConfigPath

<System.String>] [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-PublicFqdn] [-SubscriptionId <System.String>]
[-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

Import and merge Kubectl config for a managed Kubernetes Cluster.

PARAMETERS

-Admin <System.Management.Automation.SwitchParameter>

Get the 'clusterAdmin' kubectl config instead of the default 'clusterUser'.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ConfigPath <System.String>

A kubectl config file to create or update. Use '-' to print YAML to stdout instead. Default: %Home%/.kube/config.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Import Kubernetes config even if it is the default

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-Id <System.String>

Id of a managed Kubernetes cluster

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Aks.Models.PSKubernetesCluster>

A PSKubernetesCluster object, normally passed through the pipeline.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Name <System.String>

Name of your managed Kubernetes cluster

Required? true
Position? 1
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Returns true if import is successful

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-PublicFqdn <System.Management.Automation.SwitchParameter>

Get private cluster credential with server address to be public fqdn.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource group name

Required? true
Position? 0
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-SubscriptionId <System.String>

The ID of the subscription. By default, cmdlets are executed in the subscription that is set in the current context. If the user specifies another subscription,

the current cmdlet is executed in the subscription specified by the user. Overriding subscriptions only take effect during the lifecycle of the current cmdlet. It

does not change the subscription in the context, and does not affect subsequent cmdlets.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Aks.Models.PSKubernetesCluster

System.String

OUTPUTS

System.String

NOTES

----- Import and merge Kubectl config -----

Import-AzAksCredential -ResourceGroupName group -Name myCluster

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.aks/import-azakscredential>

