



Windows PowerShell Get-Help on Cmdlet 'Move-AzAutomationHybridRunbookWorker'

PS:\>Get-HELP Move-AzAutomationHybridRunbookWorker -Full

NAME

Move-AzAutomationHybridRunbookWorker

SYNOPSIS

Moves a runbook worker from one runbook worker group to the other.

SYNTAX

```
Move-AzAutomationHybridRunbookWorker [-ResourceGroupName] <System.String> [-AutomationAccountName]
<System.String> [-Name] <System.String>
                                     [-HybridRunbookWorkerGroupName]          <System.String>          [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
                                     -TargetHybridRunbookWorkerGroupName <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Move-AzAutomationHybridRunbookWorker cmdlet moves a runbook worker from one runbook worker group to the other.

PARAMETERS

-AutomationAccountName <System.String>

The automation account name.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-HybridRunbookWorkerGroupName <System.String>

The hybrid runbook worker group name

Required? true

Position? 3

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The Hybrid Runbook Worker name

Required? true

Position? 2

Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-TargetHybridRunbookWorkerGroupName <System.String>

The target hybrid runbook worker group name

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Management.Automation.Models.HybridRunbookWorker

NOTES

----- Example 1 -----

Move-AzAutomationHybridRunbookWorker -AutomationAccountName "Contoso17" -Name "RunbookWorkerName"
-HybridRunbookWorkerGroupName "RunbookWorkerGroupName"
-TargetHybridRunbookWorkerGroupName "TargetHybridRunbookWorkerGroupName" -ResourceGroupName "ResourceGroupName"

"contosoRG"

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.automation/move-azautomationhybridrunbookworker>