



Windows PowerShell Get-Help on Cmdlet 'Move-SFTPItem'

PS:\>Get-HELP Move-SFTPItem -Full

NAME

Move-SFTPItem

SYNOPSIS

Move or rename a specified item in a SFTP session.

SYNTAX

Move-SFTPItem [-SessionId] <Int32[]> [-Path] <String> [-Destination] <String> [<CommonParameters>]

Move-SFTPItem [-SFTPSession] <SftpSession[]> [-Path] <String> [-Destination] <String> [<CommonParameters>]

DESCRIPTION

Move or rename a specified item in a SFTP session.

PARAMETERS

-SessionId <Int32[]>

Session Id of an existing SFTPSession.

Required? true
Position? 1
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-SFTPSession <SftpSession[]>

Existing SFTPSession object.

Required? true
Position? 1
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Path <String>

Full path of item to be moved.

Required? true
Position? 2
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Destination <String>

New destination full path.

Required? true
Position? 3
Default value None
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

NOTES

----- Example 1 -----

```
PS C:\> Move-SFTPItem -SessionId 0 -Path "/tmp/dev_app" -Destination "/usr/local/share/app"
```

Move a folder in to /usr/local with a new name.

RELATED LINKS

Online Version: <https://github.com/darkoperator/Posh-SSH/tree/master/docs>