



Windows PowerShell Get-Help on Cmdlet 'New-AzAutomanageConfigProfile'

PS:\>Get-HELP New-AzAutomanageConfigProfile -Full

NAME

New-AzAutomanageConfigProfile

SYNOPSIS

Creates a configuration profile

SYNTAX

```
New-AzAutomanageConfigProfile -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>] -Location  
<String> [-Configuration <Hashtable>] [-Tag <Hashtable>]  
[-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend  
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential  
<PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]
```

DESCRIPTION

Creates a configuration profile

-Name <String>

Name of the configuration profile.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Location <String>

The geo-location where the resource lives

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Configuration <Hashtable>

configuration dictionary of the configuration profile.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Tag <Hashtable>

Resource tags.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Automanage.Models.Api20220504.IConfigurationProfile

----- EXAMPLE 1 -----

```
PS C:\>$confprof = @{
```

```
"Antimalware/Enable"='false';
```

```
    "Backup/Enable"='false';
```

```
    "VMInsights/Enable"='true';
```

```
    "AzureSecurityCenter/Enable"='true';
```

```
    "UpdateManagement/Enable"='true';
```

```
    "ChangeTrackingAndInventory/Enable"='true';
```

```
    "GuestConfiguration/Enable"='true';
```

```
    "LogAnalytics/Enable"='true';
```

```
    "BootDiagnostics/Enable"='true'
```

```
}
```

```
New-AzAutomanageConfigProfile -ResourceGroupName automangerg -Name confpro-pwsh01 -Location eastus  
-Configuration $confprof
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.automanage/new-azautomanageconfigprofile>