



Windows PowerShell Get-Help on Cmdlet 'New-AzAutomationHybridRunbookWorker'

PS:\>Get-HELP New-AzAutomationHybridRunbookWorker -Full

NAME

New-AzAutomationHybridRunbookWorker

SYNOPSIS

Create a Runbook Worker.

SYNTAX

```
New-AzAutomationHybridRunbookWorker [-ResourceGroupName] <System.String> [-AutomationAccountName]
<System.String> [-Name] <System.String>
                                     [-HybridRunbookWorkerGroupName]          <System.String>          [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
-VmResourceId <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The New-AzAutomationHybridRunbookWorker cmdlet creates a Runbook Worker.

-AutomationAccountName <System.String>

The automation account name.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-HybridRunbookWorkerGroupName <System.String>

The hybrid runbook worker group name

Required? true

Position? 3

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

The Hybrid Runbook Worker name

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-VmResourceId <System.String>

The resource id of the vm to be added to the hybrid worker group

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Management.Automation.Models.HybridRunbookWorker

NOTES

----- Example 1 -----

```
New-AzAutomationHybridRunbookWorker -AutomationAccountName "Contoso17" -Name "RunbookWorkerName"
-HybridRunbookWorkerGroupName "RunbookWorkerGroupName" -VmResourceId
"VmResourceId" -ResourceGroupName "ResourceGroup01"
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.automation/new-azautomationhybridrunbookworker>