



Windows PowerShell Get-Help on Cmdlet 'New-AzConfidentialLedgerCertBasedSecurityPrincipalObject'

PS:\>Get-HELP New-AzConfidentialLedgerCertBasedSecurityPrincipalObject -Full

NAME

New-AzConfidentialLedgerCertBasedSecurityPrincipalObject

SYNOPSIS

Create an in-memory object for CertBasedSecurityPrincipal.

SYNTAX

New-AzConfidentialLedgerCertBasedSecurityPrincipalObject [-Cert <String>] [-LedgerRoleName <LedgerRoleName>]
[<CommonParameters>]

DESCRIPTION

Create an in-memory object for CertBasedSecurityPrincipal.

PARAMETERS

-Cert <String>

Public key of the user cert (.pem or .cer).

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-LedgerRoleName <LedgerRoleName>

LedgerRole associated with the Security Principal of Ledger.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.ConfidentialLedger.Models.Api20220513.CertBasedSecurityPrincipal

----- EXAMPLE 1 -----

PS C:\>New-AzConfidentialLedgerCertBasedSecurityPrincipalObject `

-Cert

"-----BEGIN

CERTIFICATE-----*****
Page 2/3

*****-----END

CERTIFICATE-----" `

-LedgerRoleName "Reader"

RELATED LINKS

<https://learn.microsoft.com/powershell/module/Az.ConfidentialLedger/new-AzConfidentialLedgerCertBasedSecurityPrincipal>
Object