



Windows PowerShell Get-Help on Cmdlet 'New-AzCosmosDBLocationObject'

PS:\>Get-HELP New-AzCosmosDBLocationObject -Full

NAME

New-AzCosmosDBLocationObject

SYNOPSIS

Create a new CosmosDB Location Object(PSLocation).

SYNTAX

```

New-AzCosmosDBLocationObject [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-FailoverPriority
<System.Nullable`1[System.Int32]>] [-IsZoneRedundant <System.Nullable`1[System.Boolean]>] -LocationName
<System.String> [<CommonParameters>]
```

DESCRIPTION

Create a new CosmosDB Location Object(PSLocation).

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-FailoverPriority <System.Nullable`1[System.Int32]>

Failover priority of the location.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-IsZoneRedundant <System.Nullable`1[System.Boolean]>

Boolean to indicate whether or not this region is an AvailabilityZone.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-LocationName <System.String>

Name of the Location in string.

Required? true
Position? named
Default value None
Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.CosmosDB.Models.PSLocation

NOTES

----- Example 1 -----

New-AzCosmosDBLocationObject -LocationName "locationName" -FailoverPriority 2 -IsZoneRedundant 0

LocationName	FailoverPriority	IsZoneRedundant
--------------	------------------	-----------------

-----	-----	-----
{locationName}	2	False

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.cosmosdb/new-azcosmosdblocationobject>