



Windows PowerShell Get-Help on Cmdlet 'New-AzDataBoxEdgeDevice'

PS:\>Get-HELP New-AzDataBoxEdgeDevice -Full

NAME

New-AzDataBoxEdgeDevice

SYNOPSIS

Configures a new Data Box Edge device

SYNTAX

New-AzDataBoxEdgeDevice [-ResourceGroupName] <System.String> [-Name] <System.String> [-AsJob] [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Location

<System.String> -Sku <System.String> [-Confirm] [-WhatIf]

[<CommonParameters>]

DESCRIPTION

The New-AzDataBoxEdgeDevice cmdlet configures a new Data Box Edge device

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Location <System.String>

Location of the device

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Resource Name

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Sku <System.String>

Available Skus are Edge, Gateway

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeDevice

NOTES

----- Example 1 -----

New-AzDataBoxEdgeDevice -ResourceGroupName resourceGroupName -Name deviceName -Location eastus -Sku Edge

deviceName resourceGroupName Edge eastus

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.databoxedge/new-azdataboxedgedevice>