



Windows PowerShell Get-Help on Cmdlet 'New-AzDiskAccess'

PS:\>Get-HELP New-AzDiskAccess -Full

NAME

New-AzDiskAccess

SYNOPSIS

Creates a Disk Access resource

SYNTAX

```
New-AzDiskAccess [-ResourceGroupName] <System.String> [-Name] <System.String> [-Location] <System.String>
[-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

DESCRIPTION

The New-AzDiskAccess cmdlet creates a Disk Access resource

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Location <System.String>

Specifies the location.

Required?	true
Position?	2
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

-Name <System.String>

Specifies the name of a disk access.

Required?	true
Position?	1
Default value	None
Accept pipeline input?	True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of a resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Compute.Automation.Models.PSDiskAccess

NOTES

----- Example 1 -----

New-AzDiskAccess -ResourceGroupName "ResourceGroup01" -Name "DiskAccess01" -Location "NorthCentralUS"

This command will create a Disk Access with given properties.

RELATED LINKS