



Windows PowerShell Get-Help on Cmdlet 'New-AzEventGridPrivateEndpointConnectionObject'

PS:\>Get-HELP New-AzEventGridPrivateEndpointConnectionObject -Full

NAME

New-AzEventGridPrivateEndpointConnectionObject

SYNOPSIS

Create an in-memory object for PrivateEndpointConnection.

SYNTAX

```
New-AzEventGridPrivateEndpointConnectionObject [-GroupId <String[]>] [-PrivateEndpointId <String>]
[-PrivateLinkServiceConnectionStateActionsRequired <String>]
[-PrivateLinkServiceConnectionStateDescription <String>] [-PrivateLinkServiceConnectionStateStatus <String>]
[-ProvisioningState <String>] [<CommonParameters>]
```

DESCRIPTION

Create an in-memory object for PrivateEndpointConnection.

PARAMETERS

-GroupId <String[]>

GroupIds from the private link service resource.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-PrivateEndpointId <String>

The ARM identifier for Private Endpoint.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-PrivateLinkServiceConnectionStateActionsRequired <String>

Actions required (if any).

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-PrivateLinkServiceConnectionStateDescription <String>

Description of the connection state.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-PrivateLinkServiceConnectionStateStatus <String>

Status of the connection.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProvisioningState <String>

Provisioning state of the Private Endpoint Connection.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.EventGrid.Models.PrivateEndpointConnection

```
PS C:\>New-AzEventGridPrivateEndpointConnectionObject -GroupId "TestId" -PrivateEndpointId "TestPrivateEndpointId"
-PrivateLinkServiceConnectionStateActionsRequired
                "TestActionsRequired"      -PrivateLinkServiceConnectionStateDescription      "TestDescription"
-PrivateLinkServiceConnectionStateStatus Approved -ProvisioningState Succeeded |
Format-List
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/Az.EventGrid/new-azeventgridprivateendpointconnectionobject>